

Exstreme Gen1 RADIUS Authentication

The example configuration below shows how to configure RADIUS for both Management and Port authentication. The server, client-ip and secrets will be unique to your environment. This example also configures and enables RADIUS accounting.

```
configure radius mgmt-access primary server 10.21.0.10 1812 client-ip
172.16.5.20 vr VR-Default
configure radius mgmt-access primary shared-secret encrypted
"#$sLBECeI3y+vi56D+JsXsSaWmuvynCERCHNm1lyy21cwRTssjdoE="
configure radius mgmt-access secondary server 10.21.0.12 1812 client-ip
172.16.5.20 vr VR-Default
configure radius mgmt-access secondary shared-secret encrypted
"#$aV4JSbB7qYJIrkN+xyFpkm8C3VhEMCvmeXg+CHuFmWCPuo9/BjA="
configure radius netlogin primary server 10.21.0.10 1812 client-ip 172.16.5.20
vr VR-Default
configure radius netlogin primary shared-secret encrypted
"#$E1KQvrolmf3rZESnOuZCzgHvxuOncnJsRCrlsGkg9URvSuQAOQ8="
configure radius netlogin secondary server 10.21.0.12 1812 client-ip
172.16.5.20 vr VR-Default
configure radius netlogin secondary shared-secret encrypted
"#$25naJ++VqZmHWFEE3p940NH+BMkvA4BL2GYj1HB1WaY1AFrIt4rQ="
configure radius-accounting netlogin primary server 10.21.0.10 1813 client-ip
172.16.5.20 vr VR-Default
configure radius-accounting netlogin primary shared-secret encrypted
"#$5f6QnmG9LhNB1pb1WQB3T+F8LlIhnl5n83AzKewrEGHPtIQkLTI="
configure radius-accounting netlogin secondary server 10.21.0.12 1813 client-ip
172.16.5.20 vr VR-Default
configure radius-accounting netlogin secondary shared-secret encrypted
"#$2vpSd5mMYX46JQvXCLYqFjRnfH4AVawx57QYAm+QufLMbiRc/Do="
enable radius
enable radius mgmt-access
enable radius netlogin
enable radius-accounting netlogin
```

The example configuration below will enable both dot1x user and MAC authentication on a port by port basis. Note that you must create a dedicated netlogin pre-authentication vlan, in this case it's called net-login.

```
“ create vlan "net-login"  
   configure vlan net-login tag 2000
```

```
“ configure netlogin vlan net-login  
   enable netlogin dot1x mac  
   configure netlogin mac authentication database-order radius  
   enable netlogin ports 1:12-46 dot1x  
   enable netlogin ports 1:12-46 mac  
   configure netlogin ports 1:12 mode mac-based-vlans  
   configure netlogin ports 1:12 restart  
   configure netlogin add mac-list ff:ff:ff:ff:ff:ff 48
```

Revision #1

Created 7 June 2022 15:08:08 by Tyler

Updated 7 June 2022 15:18:32 by Tyler