

Filesystem

- [Expanding an existing filesystem using LVM](#)

Expanding an existing filesystem using LVM

Description

This example below shows you how to expand an existing filesystem that it managed by Logical Volume Manager (LVM)

Examine the existing filesystem

This command will tell the host to rescan the host adapters after a new disk has been added.

```
## echo "----" | tee /sys/class/scsi_host/host*/scan
```

/dev/mapper/ubuntu--vg-ubuntu--lv is the filesystem I want to expand.

```
## root@dock-host-2:/mnt# df -lh
Filesystem           Size  Used Avail Use% Mounted on
tmpfs                 1.6G  1.7M  1.6G  1% /run
/dev/mapper/ubuntu--vg-ubuntu--lv   63G  17G  43G  28% /
tmpfs                 7.9G   0  7.9G  0% /dev/shm
tmpfs                 5.0M   0  5.0M  0% /run/lock
/dev/sda2              974M 163M  745M 18% /boot
tmpfs                 1.6G  4.0K  1.6G  1% /run/user/1000
```

Use lsblk to take a look at all devices available. In my example I am going to use /dev/sdb as the disk to expand the existing filesystem in the LVM. lsblk shows that is /dev/sdb is 128GB in size.

```
## root@dock-host-2:~# lsblk
NAME      MAJ:MIN RM  SIZE RO TYPE MOUNTPOINT
loop0      7:0    0 55.5M  1 loop /snap/core18/2344
loop1      7:1    0 55.5M  1 loop /snap/core18/2409
loop2      7:2    0 118.4M 1 loop /snap/docker/1779
loop3      7:3    0 61.9M  1 loop /snap/core20/1494
loop4      7:4    0 102.4M 1 loop /snap/lxd/23243
loop5      7:5    0 61.9M  1 loop /snap/core20/1518
```

```
loop6          7:6  0 117.2M 1 loop /snap/docker/1767
loop7          7:7  0  47M 1 loop /snap/snapd/16292
loop8          7:8  0  47M 1 loop /snap/snapd/16010
loop10         7:10 0 102.4M 1 loop /snap/lxd/23270
sda            8:0  0 128G 0 disk
└─sda1         8:1  0   1M 0 part
└─sda2         8:2  0   1G 0 part /boot
└─sda3         8:3  0 127G 0 part
  └─ubuntu--vg-ubuntu--lv 253:0 0 63.5G 0 lvm /
sdb            8:16 0 128G 0 disk
sr0            11:0 1 1024M 0 rom
```

The next step is to run a command to prep the new disk for the LVM format.

```
root@dock-host-2:~# pvcreate /dev/sdb
WARNING: dos signature detected on /dev/sdb at offset 510. Wipe it? [y/n]: y
Wiping dos signature on /dev/sdb.
Physical volume "/dev/sdb" successfully created.
```

Once the disk is ready we need to identify the the LVM name and use it to extend the volume with the new disk we set up.

```
root@dock-host-2:~# vgs
VG      #PV #LV #SN Attr  VSize  VFree
ubuntu-vg 1  1  0 wz--n- <127.00g 63.50g
```

Once we know the name of the Volume Group we can expand the Volume Group with the new disk.

```
root@dock-host-2:~# vgextend ubuntu-vg /dev/sdb
Volume group "ubuntu-vg" successfully extended
```

After the Volume Group has been extended we can run some commands to verify the new size. You can see in the example below that we have more space in our Volume Group.

```
root@dock-host-2:~# vgs
VG      #PV #LV #SN Attr  VSize  VFree
```

```
ubuntu-vg 2 1 0 wz--n- 254.99g <191.50g
```

```
root@dock-host-2:~# vgdisplay
--- Volume group ---
VG Name          ubuntu-vg
System ID
Format          lvm2
Metadata Areas   2
Metadata Sequence No 3
VG Access        read/write
VG Status        resizable
MAX LV           0
Cur LV           1
Open LV          1
Max PV           0
Cur PV           2
Act PV           2
VG Size          254.99 GiB
PE Size          4.00 MiB
Total PE         65278
Alloc PE / Size  16255 / <63.50 GiB
Free PE / Size   49023 / <191.50 GiB
VG UUID          CVE1jf-w4fj-FreW-Xn1p-i3gv-gzbh-GcpJdY
```

Now that the Volume Group is expanded we need to expand the Logical Volume and expand the Filesystem to use the new disk space. The commands below are used to check on the Logical Volume and then extend the Logical Volume.

```
root@dock-host-2:~# lvdisplay
--- Logical volume ---
LV Path          /dev/ubuntu-vg/ubuntu-lv
LV Name          ubuntu-lv
VG Name          ubuntu-vg
LV UUID          K5CEFt-q6tF-cjxB-wCFh-f970-CTy9-07KYYk
LV Write Access  read/write
LV Creation host, time ubuntu-server, 2021-12-19 20:48:29 +0000
LV Status        available
# open           1
LV Size          <63.50 GiB
Current LE       16255
Segments         1
Allocation       inherit
```

```
Read ahead sectors    auto
 - currently set to    256
 Block device        253:0
```

```
root@dock-host-2:~# lvextend -l +100%FREE /dev/ubuntu-vg/ubuntu-lv
Size of logical volume ubuntu-vg/ubuntu-lv changed from <63.50 GiB (16255
extents) to 254.99 GiB (65278 extents).
Logical volume ubuntu-vg/ubuntu-lv successfully resized.
```

The last step is the expand the filesystem and verify that there is more free space.

```
root@dock-host-2:~# resize2fs /dev/mapper/ubuntu--vg-ubuntu--lv
resize2fs 1.46.3 (27-Jul-2021)
Filesystem at /dev/mapper/ubuntu--vg-ubuntu--lv is mounted on /; on-line
resizing required
old_desc_blocks = 8, new_desc_blocks = 32
The filesystem on /dev/mapper/ubuntu--vg-ubuntu--lv is now 66844672 (4k)
blocks long.
```

```
root@dock-host-2:~# df -lh
Filesystem           Size  Used Avail Use% Mounted on
tmpfs                 1.6G  1.7M  1.6G  1% /run
/dev/mapper/ubuntu--vg-ubuntu--lv  251G  17G  224G  7% /
tmpfs                 7.9G   0  7.9G  0% /dev/shm
tmpfs                 5.0M   0  5.0M  0% /run/lock
/dev/sda2              974M 163M  745M 18% /boot
tmpfs                 1.6G  4.0K  1.6G  1% /run/user/1000
```